

Mobile Travel Guide – Installation Guide

(V.0.7, last update 2007-08-29)

Table of Contents

Table of Contents.....	1
Introduction.....	1
Installation for Windows Mobile Devices and Blackberry Phones.....	1
Installing with a Windows PC and bluetooth connection.....	1
Installing with a Windows PC and Nokia PC suite (Nokia phones).....	2
Installing with a Windows PC and Samsung PC Studio (Samsung phones)	2
Installing with a Windows PC and the phones internal memory card (Motorola phones)	2
Installing with a direct phone download	2

Introduction

Thank you for downloading the AudioTravel Mobile City Guide. This short manual will help you to install the application on your cell phone.

Please check www.audiotravel.com/ regularly to obtain the most recent version. For questions or recommendations you can contact us via mobile@audiotravel.com.

After testing the beta version we would love to hear what you think. Email us or fill in our short survey at www.audiotravel.com/survey.

Enjoy.

Installation for Windows Mobile Devices and Blackberry Phones

Please visit the support section on www.audiotravel.com for detailed instructions on how to install the Mobile City Guide on Windows Mobile or Blackberry devices. There you will find special help sections regarding these phones.

Installing with a Windows PC and bluetooth connection

Please note: This is the recommended installation method.

To install follow these steps:

1. Download the jar file from the AudioTravel web site
2. On your phone activate Bluetooth. Make sure that your phone is set to visible (not hidden). For details on how to do this please refer to the user manual provided by the manufacturer of your phone.
3. In Windows Explorer browse to the location where you saved the jar file. Then right click the jar file and select "Send to" then "Bluetooth device" and select your phone. Please be patient, the transfer may take several minutes.
4. On your phone accept the application by following your phones instructions.

Installing with a Windows PC and Nokia PC suite (Nokia phones)

To install, follow these steps:

1. Make sure that the Nokia PC Suite is correctly installed on your computer.
2. Connect your phone to the computer.
3. Download the jar file to your computer from the AudioTravel web site.
4. Start the Nokia application manager and browse to the location where you saved the jar file.
5. Double-click the jar file.

Installing with a Windows PC and Samsung PC Studio (Samsung phones)

To install, follow these steps:

1. Make sure that the Samsung PC Studio is correctly installed on your computer.
2. Connect your phone to the computer.
3. From the AudioTravel web site download the jar and jad files to your computer.
4. In Samsung PC Studio open file manager (click "Manage Files")
5. Copy .jad and .jar to the "Other Files" folder on your phone.
6. Disconnect phone.
7. On your phone go to "Other Files", run the jad file and install the application.

Installing with a Windows PC and the phones internal memory card (Motorola phones)

This installation method requires a phone with a memory card slot and a supported memory card such as mini SD or micro SD card for example.

To install, follow these steps:

1. Download the jar file to your computer from the AudioTravel web site.
2. Insert the phone memory card into your computer, using an adapter if necessary.
3. In Windows Explorer a new drive will appear (for example "E:\").
4. Copy the jar file to the mobile/kjava folder on the memory card. For example "E:\mobile\kjava".
5. Insert the phone memory card into the phone.
6. On your phone go to "Games" and select "Install new..."
7. Choose the jar file (for example mobile_demo) from the list and press "Install".
8. Accept any warnings that might be displayed during the installation process.

Installing with a direct phone download

Important note: the file you download has a size of 10MB. This may lead to high data charges by your phone service provider.

To install simply point your internet enabled phone to <http://audiotravel.com/wap> and select the download option.